

Channel Selector Ino

Selects each RGBA channel from multiple inputs (Source1,2,3,4).

--- Inputs ---

Source1

Source2

Source3

Source4

Any one or more images to connect and process.

You can connect up to a maximum of four images.

--- Settings ---

Red

Image

Specifies the input image to be used as the Red channel.
choose from among Source1/Source2/Source3/Source4.
You can type a value from 1 to 4 on the keyboard input.
The default value is 0.

Channel

The channel to be used as the Red channel,
choose from Red/Green/Blue/Alpha.
The default value is Red.

Green

Image

Specifies the input image to be used as the Green channel.
Options are the same as the "Red Image".

Channel

The channel to be used as the Green channel,
choose from Red/Green/Blue/Alpha.
The default value is Green.

Blue

Image

Specifies the input image to be used as the Blue channel.
Options are the same as the "Red Image".

Channel

The channel to be used as the Blue channel,

choose from Red/Green/Blue/Alpha.

The default value is Blue.

Alpha

Image

Specifies the input image to be used as the Alpha channel.

Options are the same as the "Red Image".

Channel

The channel to be used as the Alpha channel,

choose from Red/Green/Blue/Alpha.

The default value is Alpha.